


Additional Area on One Computer


1. First area already installed on computer. These files are located in C:\NPD01.
2. Insert NDP disc in CDROM. Wait for NDP Installation Screen



3. Click on Install NPD



4. Click on Next




5. Select Standard Installation and enter area number in box


6. Click on Next




7. Click on Browse




8. Click in are at the top C:\NPD01 and backspace to erase the 01. Insert new area number i.e. 9999



9. Click OK




10. Click on Next




11. Select New and click on Next




12. Click at top and add new area number i.e. 9999 and click on Next




13. Click on Next




14. Wait for installation to complete




15. Click on finish



16. When back to the Installation Menu, click on Update My NPD to install update.
17. Once update has completed, select Quit
18. Open shortcut to New area and open NPD Tools and download newest update
19. Enter password: update and check remember password
20. Once down loaded, install update. It will search for copies of NPD on your computer.
21. Click on Next and highlight the new area C:\NPD9999. and click next




22. Notice the new area. Click on Next and let installation complete




23. Click on finish....

24. You can open the ShortCut to NPD9999

25. Right click on NPD and select rename



26. Left click on Icon



27. Right click on NPD Icon and drag to desk top and release, say create new short cut

28. You will now have and Icon named NPD9999

29. Now you may delete the other Icon Shortcut to NPD9999